NAME

TIFFFieldPassCount - Get whether to pass a count to TIFFGet/SetField

SYNOPSIS

#include <tiffio.h>

int TIFFFieldPassCount(const TIFFField* fip)

DESCRIPTION

TIFFFieldPassCount returns true (nonzero) if **TIFFGetField** and **TIFFSetField** expect a *count* value to be passed before the actual data pointer.

fip is a field information pointer previously returned by TIFFFindField, TIFFFieldWithTag, or TIFFFieldWithName.

When a *count* is required, it will be of type **uint32** when **TIFFFieldReadCount** reports **TIFF_VARI-ABLE2**, and of type **uint16** otherwise. (This distinction is critical for use of **TIFFGetField**, but normally not so for use of **TIFFSetField**.)

RETURN VALUES

TIFFFieldPassCount returns an integer that is always 1 (true) or 0 (false).

SEE ALSO

libtiff(3TIFF),

Libtiff library home page: http://www.simplesystems.org/libtiff/